
Subject: Re: [fatal error:] on Centos 7

Posted by [amrein](#) on Thu, 29 Dec 2016 22:21:41 GMT

[View Forum Message](#) <> [Reply to Message](#)

This is not an executable but an object file.

What is missing: var files describing all assemblies. They are created when you start theide and also by doinstall. You don't use theide so they are not there yet.

Let do this from a clean install shall we.

First, let remove ~/upp and ~/.upp

```
rm -fr ~/upp
rm -fr ~/.upp
```

Then:

```
# Do the same thing as before
cp -r /usr/share/upp ~/
mkdir -p ~/.upp/theide
cp /usr/share/upp/GCC.bm ~/.upp/theide/
cd ~/upp/
```

but also create those var files

```
echo -e "UPP = \"\$HOME/upp/uppsrc\"\nOUTPUT = \"\$HOME/upp.out\"" >
~/.upp/theide/uppsrc.var
echo -e "UPP = \"\$HOME/upp/examples;\$HOME/upp/uppsrc\"\nOUTPUT = \"\$HOME/upp.out\"" >
~/.upp/theide/examples.var
echo -e "UPP = \"\$HOME/upp/reference;\$HOME/upp/uppsrc\"\nOUTPUT = \"\$HOME/upp.out\"" >
~/.upp/theide/reference.var
echo -e "UPP = \"\$HOME/upp/tutorial;\$HOME/upp/uppsrc\"\nOUTPUT = \"\$HOME/upp.out\"" >
~/.upp/theide/tutorial.var
```

```
echo -e "UPP = \"\$HOME/upp/bazaar;\$HOME/upp/uppsrc\"\nOUTPUT = \"\$HOME/upp.out\"" >
~/.upp/theide/examples-bazaar.var
```

```
echo -e "UPP = \"\$HOME/MyApps;\$HOME/upp/uppsrc\"\nOUTPUT = \"\$HOME/upp.out\"" >
~/.upp/theide/MyApps.var
```

```
echo -e "UPP = \"\$HOME/MyApps;\$HOME/upp/bazaar;\$HOME/upp/uppsrc\"\nOUTPUT =
\"\$HOME/upp.out\"" > ~/.upp/theide/MyApps-bazaar.var
```

Build SocketServer

```
umk reference SocketServer GCC -absv
```

Run, test and kill the server

~/upp.out/SocketServer/GCC.Debug.Debug_Full.Main.Shared/SocketServer &

echo time | nc localhost 3214

killall SocketServer
