
Subject: Disable/re-enable printf()/Cout() console output

Posted by [koldo](#) on Tue, 11 Aug 2020 09:09:24 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
void ConsoleOutputDisable(bool disable) {
#ifdef PLATFORM_WIN32
    if (disable)
        freopen("nul", "w", stdout);
    else
        freopen("CONOUT$", "w", stdout);
#else
    static int saved_id = Null;
    static fpos_t saved_pos;

    if (disable) {
        fflush(stdout);
        fgetpos(stdout, &saved_pos);
        saved_id = dup(fileno(stdout));
        close(fileno(stdout));
    } else {
        if (!IsNull(saved_id)) {
            fflush(stdout);
            dup2(saved_id, fileno(stdout));
            close(saved_id);
            clearerr(stdout);
            fsetpos(stdout, &saved_pos);
        }
    }
#endif
}
```
