
Subject: Re: Upp 2007.1beta2 released
Posted by [mirek](#) on Wed, 24 Jan 2007 23:20:41 GMT
[View Forum Message](#) <> [Reply to Message](#)

Quote:

Quote:

Main configuration? (There is no "GUI MT SHARED" in build method).

Yeah, used the wrong name.

The main configuration forgets newly created configs immediately after the dialog is closed. The toolbar textbox is then empty. When pressing the build button, it falls back to "GUI".

I can launch theide-605 and then it works again. I successfully built theide-2007-b2 with it.

My guess is that it tries to write to a file under /usr/local and silently fails, when it can't due to file permissions. But just a guess.

Well, that sounds reasonable explanation. It gets stored to the "package description" file which is inside package directory.

So if you have tried to modify main config of some package inside /usr/local, it had to fail.

Quote:

Where does upp get the text color, and why would it default to grey instead of black?

Unfortunately, I am afraid I have a clue...

The problem is that there is no function available to get that individual color in Gtk API - you have to retrieve the pointer to the whole structure. Current U++ is designed to avoid including any Gtk headers, so we have to recreate the structure (see CtrlLib/ChGtk.cpp, beginning of file...). If layout changes between Gtk versions, we are in trouble...

Apparent solution is to start including gtk headers. But I wanted to try first....
