
Subject: Re: UDP connection

Posted by [Zbych](#) on Thu, 19 Apr 2012 18:32:29 GMT

[View Forum Message](#) <> [Reply to Message](#)

There are two packages in bazaar: UrrPingClient and UrrPingServer.

Here you have simple Linux udp server. On windows you need to add some winsock initialization.

```
#include <Core/Core.h>
#include <arpa/inet.h>
```

```
using namespace Upp;
```

```
CONSOLE_APP_MAIN
```

```
{
int sock = socket(AF_INET, SOCK_DGRAM, IPPROTO_UDP);
if(sock < 0) {
    RLOG("SOCK ERROR");
    return;
}
```

```
sockaddr_in srvadr;
srvadr.sin_family = AF_INET;
srvadr.sin_port = htons(9999);
srvadr.sin_addr.s_addr = htonl(INADDR_ANY);
if(bind(sock, (sockaddr *) &srvadr, sizeof(srvadr)) != 0) {
    RLOG("SOCK BIND ERROR");
    close(sock);
    return;
}
```

```
struct sockaddr addr;
socklen_t addr_size = sizeof(addr);
char buff[256];
```

```
while(1){
    ssize_t len = recvfrom(sock, buff, sizeof(buff), 0, &addr, &addr_size);
    if (len > 0){
        Cout() << Format("%d.%d.%d.%d: '%s'",
            addr.sa_data[2], addr.sa_data[3], addr.sa_data[4], addr.sa_data[5], String(buff, len));
    }
}
```

```
close(sock);
}
```
