

---

Subject: GridCtrl: how to disable the past at a given row

Posted by [forlano](#) on Thu, 11 Jan 2007 00:23:33 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

my app has a gridctrl with a fixed number of rows, say 10. So I need to disable the "past" that add rows further this limit.

If this cannot be done how to disable the whole "past" method?

Luigi

---

---

Subject: Re: GridCtrl: how to disable the past at a given row

Posted by [unodgs](#) on Thu, 11 Jan 2007 09:49:12 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

forlano wrote on Wed, 10 January 2007 19:23Hello,

my app has a gridctrl with a fixed number of rows, say 10. So I need to disable the "past" that add rows further this limit.

If this cannot be done how to disable the whole "past" method?

Luigi

Such need seem to be reasonable. I will add a proper switch before a new dev.

Unfortunately it can't be disabled right now - I will add it too, just forgot to do it in 701-dev1.

---

---

Subject: Re: GridCtrl: how to disable the past at a given row

Posted by [unodgs](#) on Thu, 11 Jan 2007 23:23:06 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Ok. Both options are implemented and in uvs.

---

---

Subject: Re: GridCtrl: how to disable the past at a given row

Posted by [forlano](#) on Thu, 11 Jan 2007 23:35:41 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

unodgs wrote on Fri, 12 January 2007 00:23Ok. Both options are implemented and in uvs.

Thank you very much Daniel. I'll wait the next dev.

Can you remind me the magic words of the new methods?

Luigi

---

---

Subject: Re: GridCtrl: how to disable the past at a given row

Posted by [forlano](#) on Tue, 16 Jan 2007 23:51:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

unodgs wrote on Fri, 12 January 2007 00:23Ok. Both options are implemented and in uvs.

I've downloaded the 701-beta and seems OK.

In this release is it possible enable/disable the paste?

... and what about the method that performs a past without overcome the last row? (I was unable to find such a method)

Thanks a lot,  
Luigi

---

Subject: Re: GridCtrl: how to disable the past at a given row

Posted by [unodgs](#) on Wed, 17 Jan 2007 07:13:48 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

forlano wrote on Tue, 16 January 2007 18:51unodgs wrote on Fri, 12 January 2007 00:23Ok.  
Both options are implemented and in uvs.

I've downloaded the 701-beta and seems OK.

In this release is it possible enable/disable the paste?

... and what about the method that performs a past without overcome the last row? (I was unable to find such a method)

Thanks a lot,  
Luigi

Disable:  
`grid.Clipboard(false)`

Paste without overcome:  
`grid.PasteFixed()`

Disabling paste as new rows/inserted rows

`grid.ExtraPaste(false)`

PS: This should be mentioned in changelog.txt (always see there )

PS2: I'm not sure about name PasteFixed if it is correct, if you have better idea please tell me.

---

Subject: Re: GridCtrl: how to disable the past at a given row

Posted by [forlano](#) on Wed, 17 Jan 2007 08:18:58 GMT

---

unodgs wrote on Wed, 17 January 2007 08:13

PS: This should be mentioned in changelog.txt (always see there )

oops... I missed it although I look at. In the top I saw 0.95 and then stop to watch further

Quote:

PS2: I'm not sure about name PasteFixed if it is correct, if you have better idea please tell me.

It's OK.

Thanks

Luigi

---