Subject: Re: Install script for Ubuntu Posted by dolik.rce on Tue, 12 Apr 2011 06:18:40 GMT View Forum Message <> Reply to Message Hi Neil nlneilson wrote on Tue, 12 April 2011 02:25I don't recall having this problem before. Upp has been running OK after install with: sudo add-apt-repository ppa:dolik-rce/upp-nightly sudo apt-get update sudo apt-get install upp I tried to update with: sudo apt-get update this is just the upp portion Ign http://ppa.launchpad.net/dolik-rce/upp-nightly/ubuntu/ maverick/main Translation-en Ign http://ppa.launchpad.net/dolik-rce/upp-nightly/ubuntu/ maverick/main Translation-en_US sudo apt-get install upp Reading package lists... Done Building dependency tree Reading state information... Done The following packages will be upgraded: upp 1 upgraded, 0 newly installed, 0 to remove and 46 not upgraded. Need to get 34.2MB of archives. After this operation, 4,313kB of additional disk space will be used. Get:1 http://ppa.launchpad.net/dolik-rce/upp-nightly/ubuntu/ maverick/main upp all 3332-1~maverick0 [34.2MB] Fetched 34.2MB in 1min 39s (344kB/s) (Reading database ... 170376 files and directories currently installed.) Preparing to replace upp 3280-1~maverick0 (using .../upp 3332-1~maverick0 all.deb) ... Unpacking replacement upp ... Setting up upp (3332-1~maverick0) ...

When Thelde is run it still shows 3280 and not 3332.

Probably some basic error on my part.

What happened is that only the U++ sources (package upp) got updated. Theide "version" is the version of sources used for its compilation, so since you had not updated it was showing lower version number - so far everything is correct.

Now the mystery is why theide didn't update as well... Are you sure you didn't mark theide to hold the version 3280 in synaptic/aptitude/apt-get/...?

nlneilson wrote on Tue, 12 April 2011 02:25With the update manager it then showed upp would be updated, which I did also which required a reboot and then I get 3332.

Perhaps when using "update ~ install" from the command line a reboot is necessary also.

Or maybe after the first install any updates should be done through Synaptic. Uh, reboot? And it really helped? Ubuntu is closer to windows than I thought Ok, now seriously: none of the packages should require reboot to work/update. To get the new version of theide just open a new instance after updating and it will start the new version. With the new updating mechanism (theide 3307 and newer), theide gets aware (if set up to do so) of the new sources while running. The older versions needed to manualy copy the sources from /usr/share/upp to your local nests in /home/<user>/upp (in the default setup).

Does this clarify it?

Best regards, Honza

Page 2 of 2 ---- Generated from U++ Forum