
Subject: how to use umk without theide?

Posted by [bonami](#) on Mon, 15 Jul 2013 09:00:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

(I want to upload my code to launchpad and let it compile my upp project.)

I installed the whole upp pack on my Ubuntu. (I do not remember the package I used.)

Then I tried

```
umk MyApps app GCC -brv +GUI,SHARED ~/.upp/_out
```

But it complained

Quote: fatal error: Web/Web.h: No such file or directory
compilation terminated.

```
g++ -c -I"/home/me/MyApps" -I"/home/me/upp/uppsrc" -I"/usr/include/freetype2"
-I"/usr/include/gtk-2.0" -I"/usr/include/glib-2.0" -I"/usr/lib/glib-2.0/include" -I"/usr/lib/gtk-2.0/include"
-I"/usr/include/cairo" -I"/usr/include/pango-1.0" -I"/usr/include/atk-1.0"
-I"/usr/include/gdk-pixbuf-2.0" -I"/usr/lib/i386-linux-gnu/glib-2.0/include"
-I"/usr/lib/x86_64-linux-gnu/glib-2.0/include" -I"/usr/lib/i386-linux-gnu/gtk-2.0/include"
-I"/usr/lib/x86_64-linux-gnu/gtk-2.0/include" -I"/usr/include/gtk-3.0/gdk" -DflagGUI -DflagSHARED
-DflagMAIN -DflagGCC -DflagBLITZ -DflagLINUX -DflagPOSIX -DbmYEAR=2013
-DbmMONTH=7 -DbmDAY=15 -DbmHOUR=15 -DbmMINUTE=22 -DbmSECOND=15
-DULTIMATEPP -fexceptions -Os -finline-limit=20 -ffunction-sections -fdata-sections
"/home/me/.upp/_out/app/GCC.Blitz.Gui.Main.Shared/$blitz.cpp " -o
"/home/me/.upp/_out/me/GCC.Blitz.Gui.Main.Shared/$blitz.o"
```

I guess if I run theide for the first time, it will ask to copy files to ~/.upp/uppsrc. But a launchpad server will not do that and umk should not rely on that.

EDIT: Changed code -> quote, to allow breaking the long commandline.
