

---

Subject: [BUG?] MIValue  
Posted by [omari](#) on Tue, 24 Mar 2015 16:54:35 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

i have added some RLOGs :

Gdb\_MI2.cpp,lines 1764 and 1773:

```
RLOG(">>>=====");
```

```
MICmd("gdb-set disassembly-flavor intel");  
MICmd("gdb-set exec-done-display off");  
MICmd("gdb-set annotate 1");  
MICmd("gdb-set height 0");  
MICmd("gdb-set width 0");  
MICmd("gdb-set confirm off");  
MICmd("gdb-set print asm-demangle");  
RLOG("<<<=====");
```

MIValue.cpp, line 457: RLOG(string);

MIValue.cpp, line 536: RLOG("String &MIValue::Get(void)");

output :

```
>>>=====  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
error:Not a String value type  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
error:Not a String value type  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
error:Not a String value type  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
String &MIValue::Get(void)  
error:Not a String value type  
String &MIValue::Get(void)
```

```
String &MValue::Get(void)
String &MValue::Get(void)
String &MValue::Get(void)
error:Not a String value type
String &MValue::Get(void)
String &MValue::Get(void)
String &MValue::Get(void)
String &MValue::Get(void)
error:Not a String value type
String &MValue::Get(void)
String &MValue::Get(void)
String &MValue::Get(void)
String &MValue::Get(void)
error:Not a String value type
String &MValue::Get(void)
String &MValue::Get(void)
<<<=====
```

Question :

Why "String &MValue::Get(void)" is called ?

