

---

Subject: QTF Table row height

Posted by [rbmatt](#) on Sun, 30 Jul 2006 17:02:39 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Is there anyway to set a height for a row in a table? I will be printing out labels, so I will have X columns by Y rows per page, and each cell needs to be exactly the right size.

As a hack I think I could put in a dummy row with width 1 and an object that is the height I need, but I'd like to know if there's anything already built-in.

Thanks

---

---

Subject: Re: QTF Table row height

Posted by [mirek](#) on Sun, 30 Jul 2006 17:59:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

No.

The height of row is equal to the maximum height of cell.

What you are about to do is more or less ok. Personally, I am rather using empty line(s) with height forced by the font height.

Mirek

---

---

Subject: Re: QTF Table row height

Posted by [rbmatt](#) on Sun, 30 Jul 2006 18:10:10 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Ok.

luzr wrote on Sun, 30 July 2006 13:59 What you are about to do is more or less ok. Personally, I am rather using empty line(s) with height forced by the font height.

I have 2 problems with that:

- I need to keep vertical alignment to center, meaning I would need to add lines before and after, and
- I do not know how many lines each cell will have until the report is generated. So a typical report would have to calculate this over 1000 times vs. once and applying it to each row.

So I'll try a dummy cell.

Thanks for the quick reply Mirek

---

---

Subject: Re: QTF Table row height

Posted by [mirek](#) on Sun, 30 Jul 2006 18:26:27 GMT

---

[View Forum Message](#) <> [Reply to Message](#)

---

...well, adding "set minimal cell height" to the ToDo...

---

---

Subject: Re: QTF Table row height  
Posted by [rbmatt](#) on Sat, 05 Aug 2006 20:25:56 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I'm having a terrible time. I have an extra row that is invisible with a single space character in it (I have tried other things).

Size sz;

Report report(sz);

int rowheight=sz.cy/rows;

The hidden cell is then printed out with (using O instead of space)

```
qtf << ":: [s0;+ " << rowheight << " O]\r\n";
```

I have the entire table setup l/0r/0t/0b/0 to kill all margins.

But my table goes for more than a page. Depending on how big "rows" is, I have one or more rows on a second page. Frame and grid are 0pt.

I also tried it by setting the top margin on my blank cell, but I got the same results.

Is there anywhere else contributing height that I am not considering?

BTW, I tried using undocumented ^^ to force a new page, but it messed up the table. Cell 1:1 went to the next page but 1:2 and 1:x were still on the same page. For now I am just letting report handle pages.

---

---

Subject: Re: QTF Table row height  
Posted by [mirek](#) on Sun, 06 Aug 2006 06:29:42 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Well, hard to say from the description. Would it be possible to create a testcase? (could be bug).

Mirek

---