
Subject: Exclamation doesnt show the text...

Posted by [kbyte](#) on Tue, 08 Jul 2008 08:44:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

When I try the UWord example the exclamation functions show the messagebox windows but text doesn't appear.

I have a very simple sample app that demonstrates this problem. Here is it:

aaa.h

```
#ifndef _aaa_aaa_h
#define _aaa_aaa_h

#include <CtrlLib/CtrlLib.h>

using namespace Upp;

#define LAYOUTFILE <aaa/aaa.lay>
#include <CtrlCore/lay.h>

class aaa : public WithaaaLayout<TopWindow>
{
public:
    typedef aaa CLASSNAME;
    aaa();
};

#endif
```

aaa.cpp

```
#include "aaa.h"
aaa::aaa()
{
    CtrlLayout(*this, "Window title");
    Exclamation("dfsdfasdfasdfsadf");
}

GUI_APP_MAIN
{
    aaa().Run();
}
```

There is a printsreen in attachment that shows the "empty" message box.

Thank you very much,

Kim

Subject: Re: Exclamation doesnt show the text...

Posted by [kbyte](#) on Tue, 08 Jul 2008 08:46:15 GMT

[View Forum Message](#) <> [Reply to Message](#)

Here is the printsreen

Kim

File Attachments

1) [aaa.JPG](#), downloaded 388 times

Subject: Re: Exclamation doesnt show the text...

Posted by [forlano](#) on Tue, 08 Jul 2008 12:36:52 GMT

[View Forum Message](#) <> [Reply to Message](#)

kbyte wrote on Tue, 08 July 2008 10:44Hi,

When I try the UWord example the exclamation functions show the messagebox windows but text
doesnt appear.

...Kim

Hello,

please post even the .lay file. But better is to post the zipped directory containing the test
package.

luigi

Subject: Re: Exclamation doesnt show the text...

Posted by [kbyte](#) on Tue, 08 Jul 2008 13:00:32 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi, and thank you.

Here is the test application zip package

Kim

File Attachments

1) [aaa.zip](#), downloaded 380 times

Subject: Re: Exclamation doesnt show the text...

Posted by [mirek](#) on Tue, 08 Jul 2008 13:50:50 GMT

[View Forum Message](#) <> [Reply to Message](#)

For me, it works as expected.

Which version of U++ are you using?

Mirek

Subject: Re: Exclamation doesnt show the text...

Posted by [kbyte](#) on Tue, 08 Jul 2008 14:06:19 GMT

[View Forum Message](#) <> [Reply to Message](#)

version 2007.1 on win xp.

For now I have to use this version. Maybe on the future I download the later one.

It happens also in the UWork sample...

The text is not shown but is shows something in a light blue on the exnd of the siposed text position... Please see the print screen

Thank you

Kim

Subject: Re: Exclamation doesnt show the text...

Posted by [mirek](#) on Tue, 08 Jul 2008 16:10:26 GMT

[View Forum Message](#) <> [Reply to Message](#)

I think this is a bug fixed some time ago.

Too bad we are somewhat struggling to get the 2008 release out...

Mirek

Subject: Re: Exclamation doesnt show the text...

Posted by [kbyte](#) on Tue, 08 Jul 2008 16:35:38 GMT

[View Forum Message](#) <> [Reply to Message](#)

Ok, thank you. I will try to fix it by debunging into upp internals...

By the way, there was a time that I run the example above and the text was shown... Hence, sometimes it is shown other times it is not.

Thank you very much

Kim

Subject: Re: Exclamation doesnt show the text...

Posted by [tojocky](#) on Tue, 08 Jul 2008 17:36:02 GMT

[View Forum Message](#) <> [Reply to Message](#)

kbyte wrote on Tue, 08 July 2008 11:46Here is the printscreen

Kim

Download the last svn release from here. It woks fine!

Subject: Re: Exclamation doesnt show the text...

Posted by [kbyte](#) on Wed, 09 Jul 2008 10:33:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

Ok, I will download it in order to fix the problem on the 2007 version.

Look, I made a mistake on the past when I change the upp internals code instead of use inheritance and so one, but those base classes I changed was not easy to create derived classes for them... So I changed directly the core classes and now I am tied to that version and to the version I have on my PC. I have to review this...

Thanks

Kim

Subject: Re: Exclamation doesnt show the text...

Posted by [kbyte](#) on Wed, 09 Jul 2008 10:35:33 GMT

[View Forum Message](#) <> [Reply to Message](#)

By the way, how can I call the win32 MessageBox?

Kim

Subject: Re: Exclamation doesnt show the text...

Posted by [mr_ped](#) on Wed, 09 Jul 2008 10:45:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

kbyte wrote on Wed, 09 July 2008 12:33Ok, I will download it in order to fix the problem on the 2007 version.

Look, I made a mistake on the past when I change the upp internals code instead of use inheritance and so one, but those base classes I changed was not easy to create derived classes for them... So I changed directly the core classes and now I am tied to that version and to the version I have on my PC. I have to review this...

Thanks

Kim

Try to do "diff" with original sources to see how much you changed, maybe it will be not that bad, and easy to move into 2008?

Eventually if some of those patches are general and everybody can profit from them, you can try to pursue Mirek to add them into core, so you don't have to patch those later.

Subject: Re: Exclamation doesnt show the text...

Posted by [mirek](#) on Wed, 09 Jul 2008 11:42:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

kbyte wrote on Wed, 09 July 2008 06:35By the way, how can I call the win32 MessageBox?

Kim

What about Win32 API?

Mirek

Subject: Re: Exclamation doesnt show the text...

Posted by [kbyte](#) on Wed, 09 Jul 2008 18:37:54 GMT

[View Forum Message](#) <> [Reply to Message](#)

Yes, thats it, win32 API but I dont know how to call a win32 api thats why I asked how to show a win32 MessageBox

Ok, In this afternoon I doenloaded the lastest upp and I already fixed all the bounding modifications I did for the 2007 version. Now all the message boxes work but another problem arrives. It is the SetStyle function on edit boxes, but I will create another thread for this one

Thank you!

Kim
