Subject: Rep Designer Posted by Shwetha on Fri, 10 Aug 2012 07:28:00 GMT View Forum Message <> Reply to Message

Hi,

I am working on report generation. I need help in designing the format...

In the Body section there is a table[Grid] which has header & multiple rows... when the data over flows and gets into the next page, Header of the table is not repeating expect in the first page.Only the row data appears on all other pages.

Wat should be done to repeat the header of the table on all the pages ???

Thanks & Regards,

Shwetha S

File Attachments 1) test.rep, downloaded 354 times

Subject: Re: Rep Designer Posted by sergeynikitin on Fri, 10 Aug 2012 11:48:45 GMT View Forum Message <> Reply to Message

Look at my RepGen package in Bazaar. Last version is in attachment.

ReportDesigner / Report generator is very needed in U++.

If I can Help, I'l very glad to do it.

File Attachments
1) RepGen.tar.gz, downloaded 320 times

Subject: Re: Rep Designer Posted by sergeynikitin on Fri, 10 Aug 2012 11:53:31 GMT View Forum Message <> Reply to Message

This is my ReportDesigner screenshot (as part of Car Washing Service Application).

File Attachments

Subject: Re: Rep Designer Posted by Shwetha on Sat, 11 Aug 2012 04:54:20 GMT View Forum Message <> Reply to Message

Hii Surgey,

Please find my attachment...

All i want to do is now get the table header in all the pages as seen in the first page. [ie as seen in the image file : SI No, Sequence, Operation, OutPut Item, Qty, Rate, Amount, Due Date]

Could you please help me and guide me what need to be done..should i make some changes in the Report Designer ???

File Attachments
1) Screenshol.png, downloaded 314 times

Subject: Re: Rep Designer Posted by Shwetha on Sat, 11 Aug 2012 04:56:34 GMT View Forum Message <> Reply to Message

File Attachments

1) Screenshot2.png, downloaded 331 times

Subject: Re: Rep Designer Posted by sergeynikitin on Sat, 11 Aug 2012 20:11:40 GMT View Forum Message <> Reply to Message

Yes.

You must use construction in table header

hnumber -

"Number of header rows. Header rows are repeated at the beginning of every page." (See QTF Article in theide help)

In your case - draw N rows below real header with "noborders" cells.