
Subject: Re: ColumnList DnD

Posted by [unodgs](#) on Fri, 11 May 2007 21:06:07 GMT

[View Forum Message](#) <> [Reply to Message](#)

Crash is here

```
void Ctrl::WndFree()
{
    if(!top) return;
    RevokeDragDrop(GetHWND());
    ReleaseUDropTarget(top->dndtgt);
    isopen = false;
    HWND owner = GetWindow(top->hwnd, GW_OWNER);// CXL 31.10.2003 z DoRemove
    bool focus = ::GetFocus() == top->hwnd;
    LLOG("Ctrl::WndDestroy owner " << (void *)owner
        << " focus " << focus
        << " ::GetFocus() " << (void *)::GetFocus());
    if(owner && focus)// CXL 7.11.2003 presun - melo by to fungovat take a neblikat...
        ::SetFocus(owner);
    LLOG(EndIndent << "//Ctrl::WndFree() in " <<UPP::Name(this));
    delete top;
    top = NULL;
}
```

in line

```
HWND owner = GetWindow(top->hwnd, GW_OWNER);// CXL 31.10.2003 z DoRemove
```

I found better way to repeat the crash.

1. chagne column width until value 382 is in last column (see attached picture)
2. Start dragging value 382 to the left.

File Attachments

1) [column.png](#), downloaded 362 times

```
0 27548110131618212427293235378
1 28558210131619212427293235379
2 29568311131619212427293235380
3 30578411131619212427303235381
4 31588511131619222427303235382
5 32598611141619222427303235383
6 33608711141619222427303335384
7 34618811141619222527303335385
8 35628911141719222527303335386
9 36639011141719222527303336387
103764911141719222528303336388
1138659211141720222528303336389
1239669312141720222528303336390
1340679412141720222528313336391
1441689512141720232528313336392
1542699612151720232528313336393
1643709712151720232528313436394
1744719812151720232628313436395
1845729912151820232628313436396
1946731012151820232628313437397
2047741012151820232629313437398
2148751012151821232629313437399
2249761013151821232629313437400
2350771013151821232629323437401
2451781013151821242629323437402
2552791013161821242629323437403
2653801013161821242629323537404
```