Subject: GridCtrl: how to disable the past at a given row Posted by forlano on Thu, 11 Jan 2007 00:23:33 GMT

View Forum Message <> Reply to Message

Hello,

my app has a gridctrl with a fixed number of rows, say 10. So I need to disable the "past" that add rows further this limit.

If this cannot be done how to disable the whole "past" method?

Luigi

Subject: Re: GridCtrl: how to disable the past at a given row Posted by unodgs on Thu, 11 Jan 2007 09:49:12 GMT

View Forum Message <> Reply to Message

forlano wrote on Wed, 10 January 2007 19:23Hello,

my app has a gridctrl with a fixed number of rows, say 10. So I need to disable the "past" that add rows further this limit.

If this cannot be done how to disable the whole "past" method?

Luigi

Such need seem to be reasonable. I will add a proper switch before a new dev.

Unfortunately it can't be disabled right now - I will add it too, just forgot to do it in 701-dev1.

Subject: Re: GridCtrl: how to disable the past at a given row Posted by unodgs on Thu, 11 Jan 2007 23:23:06 GMT

View Forum Message <> Reply to Message

Ok. Both options are implemented and in uvs.

Subject: Re: GridCtrl: how to disable the past at a given row Posted by forlano on Thu, 11 Jan 2007 23:35:41 GMT

View Forum Message <> Reply to Message

unodgs wrote on Fri, 12 January 2007 00:23Ok. Both options are implemented and in uvs.

Thank you very much Daniel. I'll wait the next dev.

Can you remind me the magic words of the new methods?

Luigi

Subject: Re: GridCtrl: how to disable the past at a given row Posted by forlano on Tue, 16 Jan 2007 23:51:16 GMT

View Forum Message <> Reply to Message

unodgs wrote on Fri, 12 January 2007 00:23Ok. Both options are implemented and in uvs.

I've downloaded the 701-beta and seems OK.

In this release is it possible enable/disable the paste?

... and what about the method that performs a past without overcome the last row? (I was unable to find such a method)

Thanks a lot, Luigi

Subject: Re: GridCtrl: how to disable the past at a given row Posted by unodgs on Wed, 17 Jan 2007 07:13:48 GMT View Forum Message <> Reply to Message

forlano wrote on Tue, 16 January 2007 18:51unodgs wrote on Fri, 12 January 2007 00:23Ok. Both options are implemented and in uvs.

I've downloaded the 701-beta and seems OK.

In this release is it possible enable/disable the paste?

... and what about the method that performs a past without overcome the last row? (I was unable to find such a method)

Thanks a lot, Luigi

Disable:

grid.Clipboard(false)

Paste without overcome:

grid.PasteFixed()

Disabling paste as new rows/inserted rows

grid.ExtraPaste(false)

PS: This should be mentioned in changelog.txt (always see there)

PS2: I'm not sure about name PasteFixed if it is correct, if you have better idea please tell me.

Subject: Re: GridCtrl: how to disable the past at a given row Posted by forlano on Wed, 17 Jan 2007 08:18:58 GMT

View Forum Message <> Reply to Message

unodgs wrote on Wed, 17 January 2007 08:13

PS: This should be mentioned in changelog.txt (always see there)

ooops... I missed it although I look at. In the top I saw 0.95 and then stop to watch further Quote:

PS2: I'm not sure about name PasteFixed if it is correct, if you have better idea please tell me.

It's OK.

Thanks

Luigi