
Subject: Environment variables code page

Posted by [Zbych](#) on Sat, 25 Jul 2009 11:05:22 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

GetEnv function uses FromSystemCharset to convert code page, but environment variables in windows use OEM not ANSI code page. I think that there should be another function - FromOEMCharset (defined only in section PLATFORM_WIN32) and GetEnv should be split in two versions (windows and posix).

App.cpp, line ~10:

```
#ifdef PLATFORM_WIN32
String GetEnv(const char *id)
{
    return FromOEMCharset(getenv(id));
}
```

[...]

App.cpp line ~20:

```
#ifdef PLATFORM_POSIX

String GetEnv(const char *id)
{
    return FromSystemCharset(getenv(id));
}
```

[...]

Util.cpp line ~620:

```
String FromOEMCharset(const String& src)
{
    WStringBuffer b(src.GetLength());
    int q = MultiByteToWideChar(CP_OEMCP, MB_PRECOMPOSED, ~src, src.GetLength(),
(WCHAR*)~b, src.GetLength());
    if(q <= 0)
        return src;
    b.SetCount(q);
    return WString(b.ToString());
}
```